

System Requirements and Installation Instructions

INSTALL_PWS specifies system and software requirements and provides instructions for the installation of the Polarimetric Workstation Software (PWS) package.

System and software requirements:

PWS has been installed and tested on MS Windows XP Pro and MS Windows XP 64 operating systems.

PWS is a Matlab standalone 32-bit program. This distribution does not contain the source code but only the executable. There is no need to have a Matlab license in order to run this program.

Installation Instructions:

1. Download the setup.**zip** file onto your hard drive
2. Unzip the setup.**zip** file.
3. Install the Matlab running time library on your machine by double clicking on **MCRInstaller.exe** setup file.
3. Install the Polarimetric Workstation Executable on you machine by double clicking on **PWDv5r5.3_Setup.exe** setup file.
4. Reboot your machine.